

# Compiling Techniques

## Lecture 10: An Introduction to MIPS assembly

Christophe Dubach

12 October 2018

# Table of contents

- 1 Overview
- 2 Registers
- 3 Instructions
  - Arithmetic
  - Memory
  - Control Structures
  - System Calls

# Assembly program template

## `.data`

Data segment: constant and variable definitions go here (including statically allocated arrays)

- format for declarations: `name: storage_type value`
- create storage for variable of specified type with given name and value
- `var1: .word 3 # one word of storage with initial value 3`
- `array1: .space 40 # 40 bytes of storage for array1`

## `.text`

Text segment: assembly instructions go here

## Components of an assembly program

Category	Example
Comment	<code># I am a comment</code>
Assembler directives	<code>.data, .asciiz</code>
Operation mnemonic	<code>add, addi, lw, bne</code>
Register name	<code>\$zero, \$t3</code>
Address label (declaration)	<code>loop1:</code>
Address label (use)	<code>loop1</code>
Integer constant	<code>8, -4, 0xA9</code>
Character constant	<code>'h', '\t'</code>
String constant	<code>"Hello, world\n"</code>

# Hello world example

```
# Description: a simple hello world program

.data

hellostr: .asciiz "Hello, world\n"

.text

li $v0, 4          # setup print syscall
la $a0$, hellostr # argument to print string
syscall           # tell the OS to do the system call
li $v0, 10        # setup exit syscall
syscall           # tell the OS to perform the syscall
```

# Registers

- 32 general-purpose registers
- register preceded by \$ in assembly language
- two formats for addressing (name or number: \$zero or \$0)
- holds 32 bits value (= 4 bytes = 1 word)
- stack grows from high memory to low memory

# Registers

Register number	Alternative name	Description
0	\$zero	the value 0
1	\$at	assembler temporary: reserved by the assembler
2-3	\$v0-\$v1	values: from expression evaluation and function results
4-7	\$a0-\$a3	arguments: first four parameters for function (no preserved across function call)
8-15	\$t0-\$t7	temporaries (not preserved across function calls)
16-23	\$s0-\$s7	saved temporaries (preserved across function calls)
24-25	\$t8-\$t9	temporaries: (not preserved across function calls)
26-27	\$k0-\$k1	reserved for use by the interrupt/trap handler
28	\$gp	global pointer : base of global data segment
29	\$sp	stack pointer : points to last location on stack
30	\$s8/\$fp	saved value / frame pointer (preserved across function call)
31	\$ra	return address

- Special Hi and Lo registers (not shown above) holds result of multiplication and division (see example later)

# Arithmetic Instructions

- Most use three operands
- All operands are registered (no memory access)
- All operands are 4 bytes (a word)



# Arithmetic Instructions

```

add      $t0,$t1,$t2
# $t0 = $t1 + $t2;
# add as signed (2's complement) integers

sub      $t2,$t3,$t4 # $t2 = $t3 - $t4
addi     $t2,$t3, 5  # $t2 = $t3 + 5;   "add immediate"
addu     $t1,$t6,$t7 # $t1 = $t6 + $t7;  add as unsigned integers
subu     $t1,$t6,$t7 # $t1 = $t6 + $t7;  subtract as unsigned integers

mult     $t3,$t4
# multiply 32-bit quantities in $t3 and $t4, and store 64-bit
# result in special registers Lo and Hi:  (Hi,Lo) = $t3 * $t4

div      $t5,$t6
# Lo = $t5 / $t6   (integer quotient)
# Hi = $t5 mod $t6 (remainder)

mfhi     $t0
# move quantity in special register Hi to $t0:  $t0 = Hi
mflo     $t1
# move quantity in special register Lo to $t1:  $t1 = Lo

move     $t2,$t3    # $t2 = $t3

```

# Load / Store Instructions

- Memory access only allowed with explicit load and store instructions (load/store architecture)
- All other instructions use register operands
- Load
  - `lw` `register_destination, mem_source`  
copy a word (4 bytes) at source memory location to destination register
  - `lb` `register_destination, mem_source`  
copy a byte to low-order byte of destination register (sign extend higher-order bytes)
  - `li` `register_destination, value`  
load immediate value into destination register

# Load / Store Instructions

- Store
  - `sw` register\_source, mem\_destination  
store a word (4 bytes) from source register to memory location
  - `sb` register\_source, mem\_destination  
store a byte (low-order) from source register to memory location

## Example

```
.data
var1: .word 23 # declare storage for var1; initial value is 23

.text
lw $t0, var1 # load contents of mem location into register $t0: $t0 = 23
li $t1, 5     # $t1 = 5 ("load immediate")
sw $t1, var1 # store contents of $t1 into mem: var1 = 5
```

# Indirect and Based Addressing

- load address:
  - `la $t0, var1`  
copy memory address of `var1` into register `$t0`
- indirect addressing:
  - `lw $t1, ($t0)`  
load word at memory address contained in `$t0` into `$t1`
  - `sw $t2, ($t0)`  
store word in register `$t2` into memory at address contained in `$t0`
- based/indexed addressing (useful for field access in struct):
  - `lw $t2, 4($t0)`  
load word at memory address (`$t0+4`) into register `$t2`
  - `sw $t2, -12($t0)`  
store content of register `$t2` into memory at address (`$t0-12`)

# Indirect and Based Addressing

## Example

```
.data
array1:  .space  12  # declare 12 bytes of storage

.text
la $t0, array1  # load base address of array into $t0
li $t1, 5       # $t1 = 5 ("load immediate")
sw $t1, ($t0)   # first array element set to 5
li $t1, 13     # $t1 = 13
sw $t1, 4($t0)  # second array element set to 13
li $t1, -7     # $t1 = -7
sw $t1, 8($t0)  # third array element set to -7
```

## Exercise

Write the assembly program corresponding to the following C code:

```
struct point_t {
    int x;
    int y;
}

void main() {
    struct point_t p;
    int arr[12];
    p.x = 2;
    p.y = 4;
    arr[3] = 6;
}
```

## Control structures

- Branches:

```

b      target          # unconditional branch to target
beq   $t0,$t1,target  # branch to target if $t0 = $t1
blt   $t0,$t1,target  # branch to target if $t0 < $t1
ble   $t0,$t1,target  # branch to target if $t0 <= $t1
bgt   $t0,$t1,target  # branch to target if $t0 > $t1
bge   $t0,$t1,target  # branch to target if $t0 >= $t1
bne   $t0,$t1,target  # branch to target if $t0 <> $t1
  
```

All branch instructions use a target label: example

```

addi $t0, $zero, 0 # t0 = 0
addi $t1, $zero, 10 # t1 = 10
loop:
addi $t0, $t0, 1    # t0 = t0+1
blt  $t0, $t1, loop # branch to loop if t0<t1 (t0<10)
  
```

## Control structures

- Jumps:

```
j          target
# unconditional jump to program label target
```

```
jr         $t3
# jump to address contained in $t3 ("jump register")
```

- Subroutine (function) call:

```
jal label # "jump and link"
```

- copy program counter (return address) to register \$ra (return address register)
- jump to program instruction at label

```
jr $ra # "jump register"
```

- jump to return address in \$ra (stored by jal instruction)

In case of nested function calls, the return address should be saved to the stack and restored accordingly.



# System Calls

System calls are used to interface with the operating systems. For instance input/output or dynamic memory allocation.

Using system calls:

- 1 load the service number in register \$v0
- 2 load argument values in \$a0, \$a1, ...
- 3 issue the syscall instruction
- 4 retrieve return value if any

Example: printing integer on the console

```
li $v0, 1
# service 1 is print integer

add $a0, $t0, $zero
# load desired value into argument register $a0

syscall
```

## System calls tables:

Service	\$v0	Arguments	Result
print integer	1	\$a0 = integer to print	
print string	4	\$a0 = address of null-terminated string to print	
print character	11	\$a0 = character to print	
read integer	5		\$v0 = integer read
read character	12		\$v0 = character read
allocate heap memory	9	\$a0 = number of bytes to allocate	\$v0 = address of allocated memory

Next lecture:

- Introduction to Code Generation