Chapter I: Introduction

UG3 Computer Communications & Networks (COMN)

MAHESH MARINA mahesh@ed.ac.uk

Slides thanks to Myungjin Lee, and copyright of Kurose and Ross


The network core

mesh of interconnected routers

 packet-switching: hosts break application-layer messages into packets

 forward packets from one router to the next, across links on path from source to destination

each packet transmitted at full link capacity



Two key network-core functions

routing: determines sourceforwarding: move packets from destination route taken by router's input to appropriate packets router output routing algorithms routing algorithm local forwarding table header value output link 3 0100 0101 0111 1001 dest address in arriving packet's header

Properties of Packet Switching


Statistical Multiplexing

Store-and-Forward

Queueing Delay

Loss


Packet Switching: Statistical Multiplexing



Sequence of A & B packets does not have fixed pattern **statistical multiplexing**.

In TDM each host gets same slot in revolving TDM frame.

Packet-switching: store-and-forward




- takes L/R seconds to transmit (push out) L-bit packet into link at R bps
- store and forward: entire packet must arrive at router before it can be transmitted on next link
 - end-end delay = 2L/R (assuming zero propagation delay)

one-hop numerical example:

- L = 7.5 Mbits
- R = 1.5 Mbps
- one-hop transmission delay5 sec

more on delay shortly ...

Packet Switching: queueing delay, loss




queuing and loss:

- If arrival rate (in bits) to link exceeds transmission rate of link for a period of time:
 - packets will queue, wait to be transmitted on link
 - packets can be dropped (lost) if memory (buffer) fills up

How do loss and delay occur?


packets queue in router buffers

packet arrival rate to link (temporarily) exceeds output link capacity




Packet loss

- queue (aka buffer) preceding link in buffer has finite capacity
- packet arriving to full queue dropped (aka lost)
- lost packet may be retransmitted by previous node, by source end system, or not at all



^{*} Check out the Java applet for an interactive animation on queuing and loss

Four sources of packet delay




d_{proc} : nodal processing

- check bit errors
- determine output link
- typically < msec</p>

d_{queue}: queueing delay

- time waiting at output link for transmission
- depends on congestion level of router

Four sources of packet delay



d_{trans} : transmission delay

- L: packet length (bits)
- R: link bandwidth (bps)
- $d_{trans} = L/R$ $d_{trans} \text{ and } d_{prop}$ very different


d_{prop} : propagation delay

- d: length of physical link
- s: propagation speed in medium (~2x10⁸ m/sec)
 - $d_{\text{prop}} = d/s$

^{*} Check out the Java applet for an interactive animation on trans vs. prop delay

Queueing delay (revisited)

- R: link bandwidth (bps)
- L: packet length (bits)
- a: average packet arrival rate



- ❖ La/R ~ 0: avg. queueing delay small
- ❖ La/R -> I: avg. queueing delay large
- La/R > I: more "work" arriving than can be serviced, average delay infinite!




La/R ~ 0

^{*} Check out the Java applet for an interactive animation on queuing and loss

"Real" Internet delays and routes

- what do "real" Internet delay & loss look like?
- traceroute program: provides delay measurement from source to router along end-end Internet path towards destination. For all i:
 - sends three packets that will reach router i on path towards destination
 - router i will return packets to sender
 - sender times interval between transmission and reply.



"Real" Internet delays and routes

traceroute: gaia.cs.umass.edu to www.eurecom.fr


```
3 delay measurements from
                                           gaia.cs.umass.edu to cs-gw.cs.umass.edu
1 cs-gw (128.119.240.254) 1 ms 1 ms 2 ms
2 border1-rt-fa5-1-0.gw.umass.edu (128.119.3.145) 1 ms 1 ms 2 ms
3 cht-vbns.gw.umass.edu (128.119.3.130) 6 ms 5 ms 5 ms
4 jn1-at1-0-0-19.wor.vbns.net (204.147.132.129) 16 ms 11 ms 13 ms 5 jn1-so7-0-0.wae.vbns.net (204.147.136.136) 21 ms 18 ms 18 ms
6 abilene-vbns.abilene.ucaid.edu (198.32.11.9) 22 ms 18 ms 22 ms
7 nycm-wash.abilene.ucaid.edu (198.32.8.46) 22 ms 22 ms 22 ms
                                                                        trans-oceanic
8 62.40.103.253 (62.40.103.253) 104 ms 109 ms 106 ms
                                                                        link
9 de2-1.de1.de.geant.net (62.40.96.129) 109 ms 102 ms 104 ms
10 de.fr1.fr.geant.net (62.40.96.50) 113 ms 121 ms 114 ms
11 renater-gw.fr1.fr.geant.net (62.40.103.54) 112 ms 114 ms 112 ms
12 nio-n2.cssi.renater.fr (193.51.206.13) 111 ms 114 ms 116 ms
13 nice.cssi.renater.fr (195.220.98.102) 123 ms 125 ms 124 ms
14 r3t2-nice.cssi.renater.fr (195.220.98.110) 126 ms 126 ms 124 ms 15 eurecom-valbonne.r3t2.ft.net (193.48.50.54) 135 ms 128 ms 133 ms
16 194.214.211.25 (194.214.211.25) 126 ms 128 ms 126 ms
                     * means no response (probe lost, router not replying)
19 fantasia.eurecom.fr (193.55.113.142) 132 ms 128 ms 136 ms
```

^{*} Do some traceroutes from exotic countries at www.traceroute.org


Alternative core: circuit switching

end-end resources allocated to, reserved for "call" between source & dest:

- In diagram, each link has four circuits.
 - call gets 2nd circuit in top link and
 lst circuit in right link.
- dedicated resources: no sharing
 - circuit-like (guaranteed)performance
- circuit segment idle if not used by call (no sharing)
- Commonly used in traditional telephone networks



Circuit switching: FDM versus TDM




Packet switching versus circuit switching

packet switching allows more users to use network!

example:

- I Mb/s link
- each user:
 - 100 kb/s when "active"
 - active 10% of time



- circuit-switching:
 - 10 users
- packet switching:
 - with 35 users, probability > 10 active
 at same time is less than .0004 *
- Q: how did we get value 0.0004?
- Q: what happens if > 35 users?

^{*} Check out the online interactive exercises for more examples


Packet switching versus circuit switching

is packet switching a "slam dunk winner?"


- great for bursty data
 - resource sharing
 - simpler, no call setup
- excessive congestion possible: packet delay and loss
 - protocols needed for reliable data transfer, congestion control
- Q: How to provide circuit-like behavior?
 - bandwidth guarantees needed for audio/video apps
 - still an unsolved problem (chapter 7)
 - Q: human analogies of reserved resources (circuit switching) versus on-demand allocation (packet-switching)?

- End systems connect to Internet via access ISPs (Internet Service Providers)
 - Residential, company and university ISPs
- Access ISPs in turn must be interconnected.
 - So that any two hosts can send packets to each other
- Resulting network of networks is very complex
 - Evolution was driven by economics and national policies
- Let's take a stepwise approach to describe current Internet structure


Question: given millions of access ISPs, how to connect them together?




Option: connect each access ISP to every other access ISP?




Option: connect each access ISP to a global transit ISP? Customer and provider ISPs have economic agreement.




But if one global ISP is viable business, there will be competitors




But if one global ISP is viable business, there will be competitors which must be interconnected




... and regional networks may arise to connect access nets to ISPS



... and content provider networks (e.g., Google, Microsoft, Akamai) may run their own network, to bring services, content close to end users






- at center: small # of well-connected large networks
 - "tier-I" commercial ISPs (e.g., Level 3, Sprint, AT&T, NTT), national & international coverage
 - content provider network (e.g, Google): private network that connects its data centers to Internet, often bypassing tier-I, regional ISPs


Throughput

- throughput: rate (bits/time unit) at which bits transferred between sender/receiver
 - instantaneous: rate at given point in time
 - average: rate over longer period of time




Throughput (more)

• $R_s < R_c$ What is average end-end throughput?



 $R_s > R_c$ What is average end-end throughput?




bottleneck link

link on end-end path that constrains end-end throughput

Throughput: Internet scenario

- per-connection endend throughput: min(R_c,R_s,R/10)
- in practice: R_c or R_s is often bottleneck



10 connections (fairly) share backbone bottleneck link R bits/sec

More Precise Definition of Throughput

- So far we implicitly assumed transferring infinite amount of data
- More precisely,
 End-to-end Throughput = TransferSize / TransferTime
- Assuming no queueing or processing delays,
 TransferTime = RTT + TransferSize / BottleneckBandwidth
 - Ist term: propagation-related delay; 2nd term: transmission delay
- From the above, can show that throughput approaches bottleneck bandwidth as transfer size approaches infinity
- RTT dominates with infinite bandwidth
- It's all relative
 - I-MB file to I-Gbps link looks like a I-KB packet to I-Mbps link

Network as a Pipe and Bandwidth-Delay Product



- Here delay refers to propagation delay
 - Typically, RTT; could also be one-way; which one is used depends on context
- Bandwidth-delay product gives the volume of the pipe
- Example: Delay of 50 ms and bandwidth of 45 Mbps
- \Rightarrow 50 x 10⁻³ seconds x 45 x 10⁶ bits/second
- \Rightarrow 2.25 x 10⁶ bits = 280 KB data


Bandwidth-Delay Product


- Relevance: indicates the amount of data to keep in the pipe (bandwidth x RTT) in order to use network/link efficiently
 - Because it takes RTT amount of time before an acknowledgement/response from destination is received

| Link type | Bandwidth (typical) | One-way distance (typical) | Round-trip delay | BDP |
|---------------------|---------------------|----------------------------|------------------|---------|
| Dial-up | 56 kbps | 10 km | 87 µs | 5 bits |
| Wireless LAN | 54 Mbps | 50 m | 0.33 µs | 18 bits |
| Satellite | 45 Mbps | 35,000 km | 230 ms | 10 Mb |
| Cross-country fiber | 10 Gbps | 4,000 km | 40 ms | 400 Mb |

Impact of High-Speed Networks

 In such networks, latency, and not throughput, dominates our thinking about network design





A 1-MB file would fill the 1-Mbps link 80 times, but only fill the 1-Gbps link 1/12 of one time

Protocol "layers"

Networks are complex, with many "pieces":

- hosts
- routers
- links of various media
- applications
- protocols
- hardware,software

Question:

is there any hope of organizing structure of network?

.... or at least our discussion of networks?


Why layering?

dealing with complex systems:


- explicit structure allows identification, relationship of complex system's pieces
 - layered reference model for discussion
- · modularization eases maintenance, updating of system
 - change of implementation of layer's service transparent to rest of system
 - e.g., change in gate procedure doesn't affect rest of system
- layering considered harmful?

Internet protocol stack

- application: supporting network applications
 - FTP, SMTP, HTTP
- transport: process-process data transfer
 - TCP, UDP
- network: routing of datagrams from source to destination
 - IP, routing protocols
- link: data transfer between neighboring network elements
 - Ethernet, 802.11 (WiFi), PPP
- physical: bits "on the wire"



Internet hourglass



ISO/OSI reference model

- presentation: allow applications to interpret meaning of data, e.g., encryption, compression, machinespecific conventions
- session: synchronization, checkpointing, recovery of data exchange
- Internet stack "missing" these layers!
 - these services, if needed, must be implemented in application
 - needed?

application presentation session transport network link physical

